PAINTMANAGER[®] XI Paint Shop Interface (PSI) Program Configuration

Before proceeding with the following instructions ensure the needed folders have been created, shared, and have the necessary security settings. See the QRG, "**PSI Folder Configuration**", for reference.

Enable PSI				
1 Navigate to Settings, Applications Settings, General	tab and enable PSI.			
2 Select the newly visible PSI tab to configure settings	S. PSI			
Configuration	n Settings			
PAINTMANAGER® XI Color Software Application Settings File navigation button General ROS From BSMS Mixing * C:\PPG\PaintShopInterface\FromBSMS Mixing ROS ArchivedFrom BSMS Pricing Image: C:\PPG\PaintShopInterface\FromBSMS\Archive Jobs * C:\PPG\PaintShopInterface\FromBSMS\Archive Jobs * C:\PPG\PaintShopInterface\FromBSMS\Archive ROS TO BSMS (Only displays if enabled) * C:\PPG\Paint Shop Interface\To BSMS 4 Number of Archived Import Files 5	Welcome, Sys Admin Logout 2 T X Save Cancel PSI Interface Type XML 10 Interval for PSI to run (2 to 60 Minutes) Description Descrip			
Collaboration Number Of RO Days to Export 2 6 Volume Estimation Export Jobs Created in PaintManager Process Now Close Local Jobs PSI 8 9	 These folders are created in the previous step to preparation for the Paint Shop Interface configuration. Use the file navigation button to select the appropriate file path. 			

- 1 Use the file navigation button to locate and select the folder shown.
- 2 Use the file navigation button to locate and select the folder shown.
- 3 Check if BSMS supports two-way communication.
- 4 Use the file navigation button to locate and select the folder shown.
- 5 The default value for this field is OK. (This value can be increased for troubleshooting purposes.)
- 6 The default value for this field is OK

PAINTMANAGER[®] XI Paint Shop Interface Program Configuration

Configuration Settings Continued

- 7 Ensure this box is unchecked.
- 8 Use to immediately process available import files and initiate the import/export process for BSMS that is configured with an external application in Step 13.
- 9 Closes all Jobs that did not transfer from the last import from the BSMS. (Old job cleanup.)
- 10 All BSMS use XML except Mitchell which is discussed in the section below.
- 11 Set for 2 to 5 minutes for BSMS without an external app and 30 to 60 minutes for those that do.
- 12 Used only for BSMS that use an external app. (See QRG for specific BSMS to see if this is required.)
- 13 BSMS external App. (See QRG for specific BSMS for instructions.)
- 14 Currently only used by SummitCRS. (See QRG for this BSMS for instructions.)

Mitchell Configuration Settings

- Select the Mitchell Interface Type.
- 2 Automatically set for 2 hours and can't be changed.
- 3 This ID number is found in the Mitchell Software. See the Mitchell QRG for specific instructions.
- 4 ZIP code as it exists in the Mitchell database.
 - US or Canada.

	Welcome, Sys Admin	.ogout ?	$ \rightarrow$	<
	Save		Cancel	
PSI Interf	асе Туре			
Mitchell			1 🔹	
Interval fo	or PSI to run (2 to 24 H	ours)		
-	2		2 +	
Mitchell S	hop ID			
1234			3	
Mitchell S	hop Zip Code			
1234			4	
Mitchell S	hop Country			
US			5 🔹	
-				
	Mitchell®	Examp	ole	
		-		